Coils array communications protocol

Defining Frames

Commands are sent as \$Axxx where A is the command letter listed below, and xxx is a three-digit numerical value for the parameter. All commands are always 5 characters long i.e. starting with a \$, and ending with xxx, even if the command doesn't require a numerical component/parameter.

All communication is carried out at 9600 BAUD (this will be increased to either 19200, 38400, or even possible 115200 BAUD when I get time)

\$Lxxx

List stored frame data

\$Cxxx

Clear stored frame data

\$Fxxx

Start frame definition for frame xxx

\$Dxxx

Set coil-coil delay, x 1 ms

\$Pxxx

Set coil "on-time", x 100 us

\$Nxxx

Set number of coils in sequence to xxx (N)

\$Xxxx

Start coils definition from sequence value xxx, i.e. from xxx = 0 to xxx = N-1, where maximum number of coils in sequence is N-1

Note that X is set to zero when you start a frame definition

\$Yxxx

Define coil X as xxx

Note that X will increment with each definition of Y so you don't really need to use \$X000 at all

\$Gxxx

Once the system is running, this will run Sequence xxx, where sequences start with 000.

Example \$F000 \$N005 \$D030 \$P007 \$Y003 \$Y007 \$Y030 \$Y045 \$Y063 \$T000 (frame definition terminated as all details have been sent) \$F001 \$N003 \$D025 \$P006 \$Y030 \$Y045 \$Y027 \$T000

\$L000 will list the 2 frames and their parameters/coil data

\$C000 will clear all frame definitions

Defining Sequences of Frames

A Sequence is a list of Frames, with each frame having a Repeat number i.e. how many times that frame should be "displayed" before moving onto the next frame in the sequence.

\$Sxxx

Define a sequence. Note that when you define a sequence, it is simply added to the list of sequences (currently, you cannot delete sequences, only add another...)

Each sequence must have the number of frames for that sequence defined with

\$nxxx

Where xxx is how many sets (frames with repeats) are included

\$fxxx

xxx the frame number

\$rxxx

Xxx is the number of times to repeat the above defined frame

\$Saaa \$n004 \$f000 first frame \$r005 repeat frame 000 5 times \$f001 \$r010 \$f003 \$r007 \$f002 \$r010 \$Taaa Terminate the sequence definition as we've added 4 frame "sets" to the sequence The above will be stored as "Sequence 0" \$Saaa \$n002 \$f015 \$r010 \$f018 \$r020 \$Taaa The above will be stored as "Sequence 1"

To define a sequence, complete the following instructions: